



Motion Computing Software Release Note

Name	C5t & F5t BIOS A02
File Name	CF5t-A02_BIOS.zip
Release Date	October 9, 2012
This Version	A02
Replaces Version	All previous versions
Intended Users	Motion Computing C5t and F5t users
Intended Product	Motion Computing C5t and F5t Tablet PCs only
File Size	2 MB
Supported Operating System	Windows 7 (32-bit/64-bit), all versions. Windows 8 (32-bit/64-bit), all versions.

Fixes in this Release

- Fix Windows 8 loss of sensor hub device after system resume from Standby or Hibernate.
- Fix RFID module maintenance mode power switch issue.

Installation and Configuration Instructions

Note: Ensure the tablet is using AC power before installing the BIOS update.

To install the BIOS update:

1. Download the BIOS update to the directory location of your choice.
2. Unzip the file to a location on your local drive.
3. Double-click the installer and follow the prompts.
4. The update process may take some time. Do not manually power off the tablet during the update.
5. The tablet will automatically shut down after installing the BIOS.

Licensing

Refer to your applicable end-user licensing agreement for usage terms.